

tikz-palattice - draw particle accelerator lattices with TikZ

Jan Schmidt <schmidt@physik.uni-bonn.de>

v2.21 (March 18, 2015)

The tikz-palattice package allows for drawing a map of a particle accelerator just by giving a list of elements - similar to lattice files for simulation software. The package includes 12 common element types like dipoles, quadrupoles, cavities or screens, as well as automatic labels with element names, a legend, a rule and an environment to fade out parts of the accelerator. The coordinate of any element can be saved and used for custom tikz drawings or annotations. Thereby, lattices can be connected to draw injection/extraction or even a complete accelerator facility.




Figure 1: The Electron Stretcher Facility ELSA at Bonn University, drawn with tikz-palattice

Copyright 2015 Jan Schmidt

Permission is granted to distribute and/or modify both the documentation and the code under the conditions of the LaTeX Project Public License, either version 1.3 of this license or (at your option) any later version. The latest version of this license is in <http://www.latex-project.org/lppl.txt>

Contents

1 Installation	2
1.1 Copy tikz-palattice.sty	2
1.2 Required packages	3
2 Basic Usage	3
3 The lattice Environment	4
4 Within lattice Environment	4
4.1 Elements	4
4.2 Orientation of the lattice	5
4.3 Rule and Legend	5
4.4 Labels	6
4.5 Colors	7
4.6 Fade Out	7
4.7 Access lattice Coordinates	8
5 Changelog	10
6 TODO	10

1 Installation

1.1 Copy tikz-palattice.sty

You just need to copy the lattice.sty file to a place where your L^AT_EX installation can recognize it. This can be

- the same folder as your .tex document or
- in the L^AT_EX system or user tree.

E.g. to add it to the system tree for texlive under ubuntu:

```
sudo mkdir -p /usr/local/share/texmf/tex/latex/lattice/  
sudo cp lattice.sty /usr/local/share/texmf/tex/latex/lattice/  
sudo mktexlsr
```

For this path there is also a Makefile prepared, so just enter

```
sudo make install
```

Otherwise read the documentation of your L^AT_EX distribution.


1.2 Required packages

- tikz
- siunitx
- ifthen
- xargs
- etoolbox

2 Basic Usage

Basically, an accelerator lattice is drawn by writing element commands one after the other. White spaces and newlines are ignored. Usually you will use one drift and one other element alternately:

```
\begin{lattice}
\source{Gun}{0.4}
\drift{0.267}
\quadrupole{Q1}{0.4}
\drift{0.29}
\dipole{M1}{0.8}{30}
\drift{0.29}
\kicker{VC1}{0.1}
\drift{0.2}
\end{lattice}
```



Descriptions of the commands are given in section 4. There are 5 examples coming with this package. Some of the drawings are shown in this document. Please look at the separate tex-files for the source code.

Some general remarks:

- it is recommended to draw lattices using `\documentclass{standalone}` especially for larger beamlines.
- lengths are set in meter, so you write `{1.32}` for 1.32 m.
- beamline with angle 0° goes to the right, positive angles bend counter clockwise.
- some commands use the TikZ *north/east/south/west* terms. *east* of an element is always where the beam leaves the element (downstream) and *west* is where the beam enters the element (upstream).

- settings (colors, font, rotatelabel, ...) changed within a `scope` environment are set back to the previous values outside of `scope`
- picture scale: for lattice `scale=1` an element of 1m length is plotted with 2 cm length

Below, the arguments of commands are given in angle brackets. The values after an equal sign are default values of optional arguments. E.g. `<scale=1>` indicates that the default value of "scale" is 1.

3 The lattice Environment

To draw a lattice just add

```
\usepackage{tikz-palattice}
```

to your preamble and use the lattice environment with

```
\begin{lattice}[<scale=1>][<tikz options=>]
...
\end{lattice}
```

The lattice environment contains a tikzpicture environment in which the lattice is drawn using usual tikz commands. The lattice environment has 2 optional arguments:

1. `<scale=1>` scales whole picture (default is 1).
2. `<tikz options=>` gives any options for the tikzpicture (e.g. overlay, default is none).

4 Within lattice Environment

4.1 Elements

Here is a list of all implemented element types. The element names are self-explanatory:

```
\drift{<length/m>}[<name=>]
\dipole{<name>}{<arc length/m>}{<bending angle/deg>}[<type=s>][<thickness/m=0.6>]
\quadrupole{<name>}{<length/m>}[<thickness/m=0.5>]
\sextupole{<name>}{<length/m>}[<thickness/m=0.3>]
\corrector{<name>}{<length/m>}[<thickness/m=0.25>]
\kicker{<name>}{<length/m>}[<thickness/m=0.25>]
\cavity{<name>}{<length/m>}[<thickness/m=0.45>]
\solenoid{<name>}{<length/m>}[<thickness/m=0.2>]
\beamdump{<name>}{<length/m>}[<thickness/m=0.5>]
\source{<name>}{<length/m>}[<thickness/m=0.5>]
\screen{<name>}[<length/m=0.2>]
\valve{<name>}
\marker{<name>}[<length/m=0.35>] % a line perpendicular to the beamline, see Fig. 2
```

The dipole option `<type=s>` allows to select different dipole shapes. It is shown in example 2. Possible values are:

- s for a sector magnet (entrance/exit surface 90 degree to beampipe)
- br for a bend rectangle magnet (parallel entrance/exit surfaces)
- r for a rectangle magnet

If you use any other letters, also the default (s) is used.




Figure 2: Example 1

4.2 Orientation of the lattice

```
\start{<coordinate/m>}
```

sets starting point of the lattice. Use it before the first element. $\langle \text{coordinate}/m \rangle$ is of form (x,y) or any tikz label, e.g. (mylabel.east) You can use this with `\savecoordinate` (section 4.7) to connect lattices, but it is recommended to do this via `\goto` (see below). Both are shown in example 3.

```
\rotate{<angle/deg>}
```

bends the beamline by the given angle.

```
\setangle{<angle/deg>}
```

sets the beamline angle to the given angle. The next element is drawn with beam axis in this direction.

```
\goto{<coordinate name>}
```

sets current position and angle to values saved with `\savecoordinate` (section 4.7). Use this to connect lattices and draw injection, extraction or even a complete accelerator facility. This is shown in example 3.

4.3 Rule and Legend

```
\drawrule{<position/m>}[<tick distance/m=1>][<scale=1>][<height/m=0.1>]
```

draws a rule to visualize the size of the lattice. Coordinate is of form (x,y) or any tikz label, e.g. (mylabel.east)

```
\legend{<position/m>}[<scale=1>]
```

draws a legend with all element types that occur in the lattice before this command. The given $\langle position/m \rangle$ is north west (upper left corner) of the legend box. The scale option scales the whole box including the text, which has the usual label textsize if $scale=1$.

```
\completelegend{\langle position/m \rangle}[\langle scale=1 \rangle]
```

is similar to `\legend`, but shows all element types.




Figure 3: From example 3

4.4 Labels

Every element has a text label showing the given element name. The position and orientation of the label is set automatically according to the current angle of the beamline. Several commands to modify the labels manually are described below. If you want to disable labels, leave the element names blank or set the label color (section 4.5) to your background color.

```
\turnlabels
```

moves labels to other side of elements (swap with marker labels), while

```
\northlabels
\southlabels
```

explicitly sets the labels to north or south (see section 2) of the elements. It is recommended to use these and not `\turnlabels`, because otherwise the label position at a certain element is determined by the number of `\turnlabels` commands before this element.

```
\rotatelabels{\langle angle/deg \rangle}[\langle anchor=\rangle]
```

allows rotation of element labels. The $\langle anchor=\rangle$ sets the center of rotation (north, center, south west, ...). West corresponds to the labels first character. By default the anchor is set automatically depending on the current angle of the beamline.

```
\begin{labeldistance}{\langle distance/m \rangle}
...
\end{labeldistance}
```

sets the distance of text labels to the element center for all elements within this environment. Default is 0.35.

```
\setlabeldistance{\langle distance/m \rangle}
\resetlabeldistance
```

sets the distance of text labels to the element center for all following elements. the reset command sets the default value. Default is 0.35.

```
\setlabelfont{\langle fontsize \rangle}
```

sets the text label font size. Default is `\normalsize`.

4.5 Colors

The colors can be changed at any point of the lattice. A setting is valid until the next color command. The reset commands set the according default color. Use a scope environment to change a color for a section of a lattice.

```
\setlinecolor{\langle type \rangle}{\langle color \rangle}
\resetlinecolor{\langle type \rangle}
```

for `\langle type \rangle` drift and marker.

```
\setelementcolor{\langle type \rangle}{\langle color \rangle}[\langle gradient color=white \rangle]
\resetelementcolor{\langle type \rangle}
```

for all element types. Set `\langle gradient color=white \rangle` equal to `\langle color \rangle` to "disable" the gradient.

```
\setlabelcolor{\langle color \rangle}
```

for textlabels. Set to background color to hide text labels.

4.6 Fade Out

```
\begin{fade}[\langle opacity=0.25 \rangle]
...
\end{fade}
```


reduces the opacity of all elements within the environment and sets all colors to gray. So you can fade out regions of the lattice - e.g. for presentations. This can also be used to completely hide regions by setting `\langle opacity=0.25 \rangle` to zero.

Custom drawings and annotations (see section 4.7) can also be faded out automatically. The tikz style faded provides the appropriate settings: Add faded to the style of any tikz drawing or node within the lattice environment. If it is drawn within a fade environment, it is faded out. Else its style is not changed:

```

\begin{lattice}
  \tikzset{mynode/.style={
    anchor=west,xshift=7mm,font=\bf,red}}
  \setangle{-90}
  \drift{0.2}
  \sextupole{S1}{0.2}
  \drift{0.267}
  \begin{fade}[0.4]
    \quadrupole{Q1}{0.4}
    \savecoordinate{Q1}[center]
    \node[mynode,faded] at (Q1) {a quadrupole!};
    \drift{0.29}
  \end{fade}
  \kicker{VC1}{0.1}
  \savecoordinate{kick}[center]
  \node[mynode,faded] at (kick) {a kicker!};
  \drift{0.2}
  \dipole{M1}{0.8}{30}
  \drift{0.29}
\end{lattice}

```



4.7 Access lattice Coordinates

You can use element coordinates to draw anything you want using pgf/tikz.

```
\savecoordinate{<name>}[<position=east>]
```

saves the coordinate of the previous element to access it later. Position specifies the exact place of the element. *east* and *center* are available (see section 2).

- you can use all tikz/pgf commands within the lattice environment to draw anything.
- You can use this to connect multiple beamlines **within a lattice environment** with `\goto{name}` (recommended, Figure 4 (b)).
- You can use this to connect **multiple lattice environments** with `\start{name}`. Use the tikz overlay option. (Figure 4 (a))




Figure 4: From example 3: Two ways to connect lattices

5 Changelog

v2.1 from 2015/02/23 is the first published version.

v2.2 from 2015/03/01

- added `\northlabels` and `\southlabels`
- minor legend improvements (label position is now independent of current lattice settings)
- minor documentation improvements

v2.21 from 2015/03/18

- added faded style (apply fade out to custom annotations)
- fixed sector dipole drawing
- documentation fixes

6 TODO

What is missing?

- manually adding and editing legend entries
- The look of the elements can be improved
- More element types can be added
- ...

I am not an TEX programmer. I basically used the TikZ commands and wrote a bunch of macros. So there is:

- no error handling implemented
- no dedicated scoping of internal macros (use of `lattice` with `documentclass standalone` recommended)

Known issues:

- A circular lattice can have a significant offset (no closed circle), if the dipole bending angles are not integer. Probably, this is due to rounding or calculation accuracy.
- Please report bugs!