

The *cloze* package*

Josef Friedrich

josef@friedrich.rocks
github.com/Josef-Friedrich/cloze

v1.0 from 2015/07/08

*Many thanks to Robert-Michael Huber for his advice and to Paul Isambert for his article "*Three things you can do with LuaTeX that would be extremely painful otherwise*" in TUGboat, Volume 31 (2010), No. 3. This article helped a lot to write this package.

Contents

1	Introduction	3
2	Usage	3
2.1	The commands and environments	3
2.1.1	<code>\cloze</code>	3
2.1.2	<code>\clozesetfont</code>	4
2.1.3	<code>\clozefix</code>	4
2.1.4	<code>\clozefil</code>	4
2.1.5	<code>clozepar</code>	5
2.1.6	<code>\clozeline</code>	5
2.1.7	<code>\clozelinefil</code>	5
2.2	The options	5
2.2.1	Local and global options	5
2.2.2	<code>\clozeset</code>	5
2.2.3	<code>\clozereset</code>	6
2.2.4	<code>\clozeshow</code> and <code>\clozehide</code>	6
2.2.5	<code>align</code>	7
2.2.6	<code>distance</code>	7
2.2.7	<code>hide</code> and <code>show</code>	7
2.2.8	<code>linecolor</code> and <code>textcolor</code>	7
2.2.9	<code>margin</code>	8
2.2.10	<code>thickness</code>	8
2.2.11	<code>width</code>	8
3	Implementation	9
3.1	The file <code>cloze.sty</code>	9
3.1.1	Internal macros	9
3.1.2	Options	10
3.1.2.1	<code>align</code>	11
3.1.2.2	<code>distance</code>	11
3.1.2.3	<code>hide</code>	11
3.1.2.4	<code>linecolor</code>	11
3.1.2.5	<code>margin</code>	12
3.1.2.6	<code>show</code>	12
3.1.2.7	<code>textcolor</code>	12
3.1.2.8	<code>thickness</code>	12
3.1.2.9	<code>width</code>	12
3.1.3	Public macros	12
3.2	The file <code>cloze.lua</code>	15
3.2.0.1	Initialisation of the function tables	15
3.2.1	Node processing (<code>nodex</code>)	16
3.2.1.1	Color handling (<code>color</code>)	16
3.2.1.2	Line handling (<code>line</code>)	16

3.2.1.3	Handling of extendable lines (linefil)	18
3.2.1.4	Kern handling (kern)	18
3.2.2	Option handling (registry)	19
3.2.2.1	Marker processing (marker)	19
3.2.2.2	Storage functions (storage)	21
3.2.2.3	Option processing (option)	21
3.2.3	Assembly to cloze texts (cloze)	23
3.2.4	Basic module functions (base)	27

1 Introduction

cloze is a \LaTeX package to generate cloze texts. It uses the capabilities of the modern \TeX engine *Lua \TeX* . Therefore, you must use *Lua \LaTeX* to create documents containing gaps.

```
lualatex cloze-text.tex
```

The main feature of the package is that the formatting doesn't change when using the `hide` and `show` (\rightarrow 2.2.7) options.

Lorem ipsum dolor sit amet, consectetur adipiscing elit, sed do eiusmod tempor incididunt ut labore et dolore magna aliqua. Ut enim ad minim veniam, quis nostrud exercitation ullamco laboris nisi ut aliquip ex ea commodo consequat.

The command `\clozeset{hide}` only shows gaps. When you put both texts on top of each other you will see that they perfectly match.

Lorem ipsum _____ amet, consectetur _____ elit, sed do eiusmod tempor incididunt ut labore et _____ aliqua. Ut enim ad minim veniam, quis nostrud _____ ullamco laboris nisi ut _____ ex ea commodo consequat.

2 Usage

There are three commands and one environment to generate cloze texts: `\cloze`, `\clozefix`, `\clozefil` and `clozepar`.

2.1 The commands and environments

2.1.1 `\cloze`

`\cloze` `\cloze[\langle options \rangle]{\langle some text \rangle}`: The command `\cloze` is similar to a command that offers the possibility to underline the texts. `\cloze` does not prevent line breaks. The width of a gap depends on the number of letters and the font used. The only option which affects the widths of a gap is the option `margin` (\rightarrow 2.2.9).

Lorem ipsum dolor sit amet, consectetur adipiscing elit, sed do eiusmod tempor incididunt ut labore et dolore magna aliqua. Ut enim ad minim veniam, quis nostrud exercitation ullamco laboris nisi ut aliquip ex ea commodo consequat.

It is possible to convert a complete paragraph into a 'gap'. But don't forget: There is a special environment for this: `clozepar` (\rightarrow 2.1.5).

Lorem ipsum dolor sit amet, consectetur adipiscing elit, sed do eiusmod tempor incididunt ut labore et dolore magna aliqua. Ut enim ad minim veniam, quis nostrud exercitation ullamco laboris nisi ut aliquip ex ea commodo consequat.

The command `\cloze` doesn't change the behavior of the hyphenation. Let's try some long German words:

es Telekommunikationsüberwachung geht Unternehmenssteuerfortentwicklungsgesetz Abteilungsleiterin Oberkommissarin auch Fillialleiterin kurz Oberkommissarin Unternehmenssteuerfortentwicklungsgesetz Fillialleiterin Metzgermeisterin in Abteilungsleiterin der Oberkommissarin Hochleistungsflüssigkeitschromatographie Fillialleiterin Kürze Unternehmenssteuerfortentwicklungsgesetz Metzgermeisterin liegt Abteilungsleiterin die Metzgermeisterin Abteilungsleiterin Würze Oberkommissarin Fillialleiterin Telekommunikationsüberwachung Hochleistungsflüssigkeitschromatographie Metzgermeisterin Abteilungsleiterin ein Oberkommissarin paar Fillialleiterin kurze Metzgermeisterin Wörter Abteilungsleiterin Oberkommissarin Fillialleiterin Metzgermeisterin

2.1.2 `\clozesetfont`

`\clozesetfont` The gap font can be changed by using the command `\clozesetfont`. `\clozesetfont` redefines the command `\clozefont` which contains the font definition. Thus, the command `\clozesetfont{\Large}` has the same effect as `\renewcommand{\clozefont}{\Large}`.

Excepteur sint occaecat cupidatat non proident.

Please do not put any color definitions in `\clozesetfont`, as it won't work. Use the option `textcolor` instead (→ 2.2.8).

`\clozesetfont{\ttfamily\normalsize}` changes the gap text for example into a normal sized typewriter font.

Excepteur sint occaecat cupidatat non proident.

2.1.3 `\clozefix`

`\clozefix` `\clozefix[options]{some text}`: The command `\clozefix` creates gaps with a fixed width. The clozes are default concerning the width 2cm.

Lorem ipsum dolor sit amet:
 1. consectetur
 2. adipiscing
 3. elit
 sed do eiusmod.

2.1.4 `\clozefil`

`\clozefil` `\clozefil[options]{some text}`: The name of the command is inspired by `\hfil`, `\hfill`, and `\hfilll`. Only `\clozefil` fills out all available horizontal spaces with a line.

Lorem ipsum dolor sit amet, consectetur adipiscing elit, sed do eiusmod.
 Ut enim ad minim veniam _____ exercitation.

2.1.5 clozepar

`clozepar` `\begin{clozepar}[\langle options \rangle] ...some text ...\end{clozepar}`: The environment `clozepar` transforms a complete paragraph into a cloze text. The options `align`, `margin` and `width` have no effect on this environment.

```

  Lorem ipsum dolor sit amet, consectetur adipiscing elit ullamco laboris nisi.
  Ut enim ad minim veniam, quis nostrud exercitation ullamco laboris nisi ut aliquip
ex ea commodo consequat. Duis aute irure dolor in reprehenderit in voluptate velit
esse cillum.
  Excepteur sint occaecat cupidatat non proident.
```

2.1.6 \clozeline

`\clozeline` `\clozeline[\langle options \rangle]`: To create a cloze line of a certain width, use the command `\clozeline`. The default width of the line is 2cm. In combination with the other cloze commands you can create for example an irregular alignment of the cloze text.

```

  Ut enim ad
  \clozeline[width=1cm]\cloze{minim}\clozeline[width=3cm]
  minim veniam
```

```

  Ut enim ad _____ minim _____ minim veniam,
```

2.1.7 \clozelinefil

`\clozelinefil` `\clozelinefil[\langle options \rangle]`: This command `\clozelinefil` fills the complete available horizontal space with a line. Moreover, `\clozelinefil` was used to create `\clozefil`.

```

  Lorem _____
```

2.2 The options

2.2.1 Local and global options

The *cloze* package distinguishes between *local* and *global* options. Besides the possibility to set *global* options in the `\usepackage[\langle global options \rangle]{\langle cloze \rangle}` declaration, the *cloze* package offers a special command to set *global* options: `\clozeset{\langle global options \rangle}`

2.2.2 \clozeset

`\clozeset` `\clozeset{\langle global options \rangle}`: The command can set *global* options for each paragraph.

```

  \clozeset{textcolor=red} Lorem \cloze{ipsum} dolor \par
  \clozeset{textcolor=green} Lorem \cloze{ipsum} dolor
```

```

Lorem ipsum dolor
Lorem ipsum dolor

```

`\clozeset` does not change the options within a paragraph. As you can see in the example below the last `\clozeset` applies the color green for both gaps.

```

\clozeset{textcolor=red} Lorem \cloze{ipsum} dolor
\clozeset{textcolor=green} Lorem \cloze{ipsum} dolor

```

```

Lorem ipsum dolor Lorem ipsum dolor

```

2.2.3 `\clozereset`

`\clozereset` `\clozereset`: The command resets all *global* options to the default values. It has no effect on the *local* options.

```

\clozeset{
  thickness=3mm,
  linecolor=yellow,
  textcolor=magenta,
  margin=-2pt
}

```

```

Very silly global options

```

```

\clozereset

```

```

Relax! We can reset those options.

```

2.2.4 `\clozeshow` and `\clozehide`

`\clozeshow` `\clozeshow` and `\clozehide`: This commands are shortcuts for `\clozeset{<show>}` and `\clozeset{<hide>}`.

```

\clozehide

```

```

Lorem _____ amet, consectetur _____ elit.

```

```

\clozeshow

```

```

Lorem ipsum dolor sit amet, consectetur adipiscing elit.

```

2.2.5 align

[align=*(left/center/right)*]: Only the macro `\clozefix` (→ 2.1.3) takes the option `align` into account. Possible values are `left`, `center` and `right`. This option only makes sense, if the width of the line is larger than the width of the text.

<i> Lorem ipsum </i>		(left)	
	<i> Lorem ipsum </i>	(center)	
		<i> Lorem ipsum </i>	(right)

2.2.6 distance

[distance=*(dimen)*]: The option `distance` specifies the spacing between the baseline of the text and the gap line. The larger the dimension of the option `distance`, the more moves the line down. Negative values cause the line to appear above the baseline. The default value is 1.5pt.

<i> Lorem ipsum dolor sit amet. </i>	(1.5pt)
<i> Lorem ipsum dolor sit amet. </i>	(3pt)
<i> Lorem ipsum dolor sit amet. </i>	(-3pt)

2.2.7 hide and show

[hide] and [show]: By default the cloze text is displayed. Use the option `hide` to remove the cloze text from the output. If you accidentally specify both options – `hide` and `show` – the last option "wins".

Lorem ipsum _____, consectetur _____ elit.	(hide)
Lorem ipsum <i> dolor sit amet </i> , consectetur <i> adipiscing </i> elit.	(show)
Lorem ipsum _____, consectetur _____ elit.	(show,hide)
Lorem ipsum <i> dolor sit amet </i> , consectetur <i> adipiscing </i> elit.	(hide,show)

2.2.8 linecolor and textcolor

[linecolor=*(color name)*] and [textcolor=*(color name)*]: Values for both color options are color names used by the `xcolor` package. To define your own color use the following command:

```
\definecolor{myclozecolor}{rgb}{0.1,0.4,0.6}
\cloze[textcolor=myclozecolor]{Lorem ipsum}
```

<i> Lorem ipsum dolor sit amet, consectetur </i>	(myclozecolor)
<i> Lorem ipsum dolor sit amet, consectetur </i>	(red)
<i> Lorem ipsum dolor sit amet, consectetur </i>	(green)

You can use the same color names to colorize the cloze lines.

<i> Lorem ipsum dolor sit amet, consectetur </i>	(myclozecolor)
<i> Lorem ipsum dolor sit amet, consectetur </i>	(red)
<i> Lorem ipsum dolor sit amet, consectetur </i>	(green)

2.2.9 margin

[**margin**=*<dimen>*]: The option **margin** indicates how far the line sticks up from the text. The option can be used with the commands `\cloze`, `\clozefix` and `\clozefil`. The default value of the option is **3pt**.

Lorem ipsum <i>dolor</i> sit amet.	(0pt)
Lorem ipsum <u> <i>dolor</i> </u> sit amet.	(5mm)
Lorem ipsum <u> <i>dolor</i> </u> sit amet.	(1cm)
Lorem ipsum <u> <i>dolor</i> </u> sit amet.	(6em)
Lorem ipsum <u><i>dolor</i></u> sit amet.	(-4pt)

Is a punctuation mark placed directly after a gap, then the line breaks after this punctuation mark. Even the most large value of **margin** does not affect this behavior.

<u> <i> Lorem </i></u> , <u> <i> ipsum </i></u> . <u> <i> dolor </i></u> ; <u> <i> sit </i></u> ; <u> <i> amet </i></u> , <u> <i> consectetur </i></u> .
<u> <i> adipiscing </i></u> ; <u> <i> elit </i></u> ; <u> <i> sed </i></u> , <u> <i> do </i></u> . <u> <i> eiusmod </i></u> ; <u> <i> tempor </i></u> .

2.2.10 thickness

[**thickness**=*<dimen>*]: The option **thickness** indicates how thick the line is. The option **distance** (→ 2.2.6) is not affected by this option, because the bottom of the line moves down. The default value of this option is **0.4pt**.

Lorem <u> <i> ipsum dolor sit </i></u> amet.	(0.01pt)
Lorem <u> <i> ipsum dolor sit </i></u> amet.	(1pt)
Lorem <u> <i> ipsum dolor sit </i></u> amet.	(2pt)

2.2.11 width

[**width**=*<dimen>*]: The only command which can be changed by the option **width** is `\clozefix` (→ 2.1.3). The default value of the option is **2cm**.

Lorem <u> <i> dolor </i></u> amet.	(3cm)
Lorem <u> <i> dolor </i></u> amet.	(5cm)
Lorem <u> <i> dolor </i></u> amet.	(7cm)

3 Implementation

3.1 The file `cloze.sty`

This four packages are used to build *cloze*:

- `fontspec` is not necessarily required. When using Lua \LaTeX it is good form to load it. Apart from this the package supplies helpful messages, when you compile a Lua \LaTeX document with pdf \LaTeX .
- `luatexbase` allows to register multiple Lua callbacks.
- `kvoptions` takes the handling of the options.
- `xcolor` is required to colorize the text and the line of a gap.

```
26 \RequirePackage{fontspec,luatexbase-mcb,kvoptions,xcolor}
```

Load the *cloze* lua module and put all return values in the variable `cloze`.

```
27 \directlua{
28   cloze = require('cloze')
29 }
```

3.1.1 Internal macros

`\cloze@set@to@global` Set the Lua variable `registry.is_global` to true. All options are then stored in the variable `registry.global_options`.

```
30 \def\cloze@set@to@global{%
31   \directlua{cloze.set_is_global(true)}%
32 }
```

`\cloze@set@to@local` First unset the variable `registry.local_options`. Now set the Lua variable `registry.is_global` to false. All options are then stored in the variable `registry.local_options`.

```
33 \def\cloze@set@to@local{%
34   \directlua{
35     cloze.unset_local_options()
36     cloze.set_is_global(false)
37   }%
38 }
```

`\cloze@set@option` `\cloze@set@option` is a wrapper for the Lua function `registry.set_option`. `\cloze@set@option[$\langle key \rangle$]{ $\langle value \rangle$ }` sets a key $\langle key \rangle$ to the value $\langle value \rangle$.

```
39 \def\cloze@set@option[#1]#2{%
40   \directlua{cloze.set_option('#1', '#2')}%
41 }
```

`\cloze@color` Convert a color definition name to a PDF colorstack string, for example convert the color name `blue` to the colorstack string `0 0 1 rg 0 0 1 RG`. The macro definition `\cloze@color{blue}` builds itself the macro `\color@blue`, which expands to the PDF colorstack string. The colorstack string is necessary to generate a PDF colorstack whatsit.

```
42 \def\cloze@color#1{\csname\string\color@#1\endcsname}
```

`\cloze@set@local@options` This macro is used in all cloze commands to handle the optional arguments. First it sets the option storage to local and then it commits the options to the package `kvoptions` via the macro `\kvsetkeys{CLZ}{}`.

```
43 \def\cloze@set@local@options#1{%
44   \cloze@set@to@local%
45   \kvsetkeys{CLZ}{#1}%
46 }
```

`\cloze@start@marker` At the beginning `\cloze@start@marker` registers the required Lua callbacks. Then it inserts a whatsit marker which marks the begin of a gap.

```
47 \def\cloze@start@marker#1{%
48   \strut\directlua{
49     cloze.register('#1')
50     cloze.marker('#1', 'start')
51   }%
52 }
```

`\cloze@stop@marker` `\cloze@stop@marker` inserts a whatsit marker that marks the end of gap.

```
53 \def\cloze@stop@marker#1{%
54   \strut\directlua{
55     cloze.marker('#1', 'stop')
56   }%
57 }
```

`\cloze@margin` `\cloze@margin` surrounds a text in a gap with two kerns.

```
58 \def\cloze@margin#1{%
59   \directlua{cloze.margin()}%
60   #1%
61   \directlua{cloze.margin()}%
62 }
```

3.1.2 Options

`cloze` offers key-value pairs to use as options. For processing the key-value pairs we use the package `kvoptions`. To make all key-value pairs accessibly to Lua code, we use the declaration `\define@key{<CLZ>}{<option>}[</>]{<...>}`. This declaration comes from the package `keyval`.

At start all values are declared as global options. At the Lua side all values are now stored in the `registry.global_options` table.

```
63 \cloze@set@to@global
```

We use the abbreviation CLZ for *cloze* as family name and prefix.

```
64 \SetupKeyvalOptions{
65   family=CLZ,
66   prefix=CLZ@
67 }
```

3.1.2.1 align

Please read the section (→ [2.2.5](#)) how to use the option `align`. `align` affects only the command `\clozefix` (→ [2.1.3](#)).

```
68 \DeclareStringOption{align}
69 \define@key{CLZ}{align}[]{\cloze@set@option[align]{#1}}
```

3.1.2.2 distance

Please read the section (→ [2.2.6](#)) how to use the option `distance`.

```
70 \DeclareStringOption{distance}
71 \define@key{CLZ}{distance}[]{\cloze@set@option[distance]{#1}}
```

3.1.2.3 hide

If the option `hide` appears in the commands, `hide` will be set to *true* and `show` to *false* on the Lua side. Please read the section (→ [2.2.7](#)) how to use the option `hide`.

```
72 \DeclareVoidOption{hide}{%
73   \cloze@set@option[hide]{true}%
74   \cloze@set@option[show]{false}%
75 }
```

3.1.2.4 linecolor

Please read the section (→ [2.2.8](#)) how to use the option `linecolor`.

```
76 \DeclareStringOption{linecolor}
77 \define@key{CLZ}{linecolor}[]{%
78   \cloze@set@option[linecolor]{\cloze@color{#1}}%
79 }
```

3.1.2.5 margin

Please read the section (→ 2.2.9) how to use the option `margin`.

```
80 \DeclareStringOption{margin}
81 \define@key{CLZ}{margin}[]{\cloze@set@option[margin]{#1}}
```

3.1.2.6 show

If the option `show` appears in the commands, `show` will be set to *true* and `true` to *false* on the Lua side. Please read the section (→ 2.2.7) how to use the option `show`.

```
82 \DeclareVoidOption{show}{%
83   \cloze@set@option[show]{true}%
84   \cloze@set@option[hide]{false}%
85 }
```

3.1.2.7 textcolor

Please read the section (→ 2.2.8) how to use the option `textcolor`.

```
86 \DeclareStringOption{textcolor}
87 \define@key{CLZ}{textcolor}[]{%
88   \cloze@set@option[textcolor]{\cloze@color{#1}}%
89 }
```

3.1.2.8 thickness

Please read the section (→ 2.2.10) how to use the option `thickness`.

```
90 \DeclareStringOption{thickness}
91 \define@key{CLZ}{thickness}[]{\cloze@set@option[thickness]{#1}}
```

3.1.2.9 width

Please read the section (→ 2.2.11) how to use the option `width`. `width` affects only the command `\clozefix` (→ 2.1.3).

```
92 \DeclareStringOption{width}
93 \define@key{CLZ}{width}[]{\cloze@set@option[width]{#1}}

94 \ProcessKeyvalOptions{CLZ}
```

3.1.3 Public macros

All public macros are prefixed with `\cloze`.

`\clozeset` The usage of the command `\clozeset` is described in detail in section (→ [2.2.2](#)).

```
95 \newcommand{\clozeset}[1]{%
96   \cloze@set@to@global%
97   \kvsetkeys{CLZ}{#1}%
98 }
```

`\clozereset` The usage of the command `\clozereset` is described in detail in section (→ [2.2.3](#)).

```
99 \newcommand{\clozereset}{%
100   \directlua{cloze.reset()}
101 }
```

`\clozeshow` The usage of the command `\clozeshow` is described in detail in section (→ [2.2.4](#)).

```
102 \newcommand{\clozeshow}{%
103   \clozeset{show}
104 }
```

`\clozhide` The usage of the command `\clozhide` is described in detail in section (→ [2.2.4](#)).

```
105 \newcommand{\clozhide}{%
106   \clozeset{hide}
107 }
```

`\clozefont` The usage of the command `\clozefont` is described in detail in section (→ [2.1.2](#)).

```
108 \newcommand{\clozefont}{\itshape}
```

`\clozesetfont` The usage of the command `\clozesetfont` is described in detail in section (→ [2.1.2](#)).

```
109 \newcommand{\clozesetfont}[1]{%
110   \renewcommand{\clozefont}[1]{%
111     #1%
112   }%
113 }
```

`\cloze` The usage of the command `\cloze` is described in detail in section (→ [2.1.1](#)).

```
114 \newcommand{\cloze}[2] []{%
115   \cloze@set@local@options{#1}%
116   \cloze@start@marker{basic}%
117   {%
118     \clozefont\relax%
119     \cloze@margin{#2}%

```

```

120 }%
121 \cloze@stop@marker{basic}%
122 }

```

`\clozefix` The usage of the command `\clozefix` is described in detail in section (→ 2.1.3).

```

123 \newcommand{\clozefix}[2] [] {%
124 \cloze@set@local@options{#1}%
125 \cloze@start@marker{fix}%
126 {%
127 \clozefont\relax%
128 \cloze@margin{#2}%
129 }%
130 \cloze@stop@marker{fix}%
131 }

```

`clozepar` The usage of the environment `clozepar` is described in detail in section (→ 2.1.5).

```

132 \newenvironment{clozepar}[1] [] {%
133 {%
134 \par%
135 \cloze@set@local@options{#1}%
136 \cloze@start@marker{par}%
137 \clozefont\relax%
138 }%
139 {%
140 \cloze@stop@marker{par}%
141 \par%
142 \directlua{cloze.unregister('par')}%
143 }

```

`\clozefil` The usage of the command `\clozefil` is described in detail in section (→ 2.1.4).

```

144 \newcommand{\clozefil}[2] [] {%
145 \cloze[#1]{#2}\clozelinefil[#1]%
146 }

```

`\clozeline` The usage of the command `\clozeline` is described in detail in section (→ 2.1.6).

```

147 \newcommand{\clozeline}[1] [] {%
148 \cloze@set@local@options{#1}%
149 \directlua{cloze.line()}%
150 }

```

`\clozelinefil` The usage of the command `\clozelinefil` is described in detail in section (→ 2.1.7).

```

151 \newcommand{\clozelinefil}[1] [] {%
152 \cloze@set@local@options{#1}%

```

```

153 \strut%
154 \directlua{cloze.linefil()}%
155 \strut%
156 }

```

3.2 The file `cloze.lua`

3.2.0.1 Initialisation of the function tables

It is good form to provide some background informations about this Lua module.

```

1 if not modules then modules = { } end modules ['cloze'] = {
2   version   = '0.1',
3   comment   = 'cloze',
4   author    = 'Josef Friedrich, R.-M. Huber',
5   copyright = 'Josef Friedrich, R.-M. Huber',
6   license   = 'The LaTeX Project Public License Version 1.3c 2008-05-04'
7 }

```

`nodex` is a abbreviation for *node eXtended*.

```

8 local nodex = {}

```

All values and functions, which are related to the option management, are stored in a table called `registry`.

```

9 local registry = {}

```

I didn't know what value I should take as `user_id`. Therefore I took my birthday and transformed it to a large number.

```

10 registry.user_id = 3121978
11 registry.storage = {}
12 registry.defaults = {
13   ['align'] = 'l',
14   ['distance'] = '1.5pt',
15   ['hide'] = false,
16   ['linecolor'] = '0 0 0 rg 0 0 0 RG', -- black
17   ['margin'] = '3pt',
18   ['resetcolor'] = '0 0 0 rg 0 0 0 RG', -- black
19   ['show_text'] = true,
20   ['show'] = true,
21   ['textcolor'] = '0 0 1 rg 0 0 1 RG', -- blue
22   ['thickness'] = '0.4pt',
23   ['width'] = '2cm',
24 }
25 registry.global_options = {}
26 registry.local_options = {}

```


All those functions are stored in the table `cloze` that are registered as callbacks to the pre and post linebreak filters.

```
27 local cloze = {}
```

The `base` table contains some basic functions. `base` is the only table of this Lua module that will be exported.

```
28 local base = {}
29 base.is_registered = {}
```

3.2.1 Node preprocessing (nodex)

All functions in this section are stored in a table called `nodex`. `nodex` is a abbreviation for *node eXtended*. The `nodex` table bundles all functions, which extend the built-in `node` library.

3.2.1.1 Color handling (color)

`create_colorstack`

Create a `whatsit` node of the subtype `pdf_colorstack`. `data` is a PDF colorstack string like `0 0 0 rg 0 0 0 RG`.

```
30 function nodex.create_colorstack(data)
31   if not data then
32     data = '0 0 0 rg 0 0 0 RG' -- black
33   end
34   local whatsit = node.new('whatsit', 'pdf_colorstack')
35   whatsit.stack = 0
36   whatsit.data = data
37   return whatsit
38 end
```

`create_color`

`nodex.create_color()` is a wrapper for the function `nodex.create_colorstack()`. It queries the current values of the options `linecolor` and `textcolor`. The argument option accepts the strings `line`, `text` and `reset`.

```
39 function nodex.create_color(option)
40   local data
41   if option == 'line' then
42     data = registry.get_value('linecolor')
43   elseif option == 'text' then
44     data = registry.get_value('textcolor')
45   elseif option == 'reset' then
46     data = nil
47   else
48     data = nil
49   end
50   return nodex.create_colorstack(data)
51 end
```

3.2.1.2 Line handling (line)

`create_line`

Create a rule node, which is used as a line for the cloze texts. The `depth` and the `height` of the rule are calculated from the options `thickness` and `distance`. The argument `width` must have the length unit *scaled points*.

```
52 function nodex.create_line(width)
53   local rule = node.new(node.id('rule'))
54   local thickness = tex.sp(registry.get_value('thickness'))
55   local distance = tex.sp(registry.get_value('distance'))
56   rule.depth = distance + thickness
57   rule.height = - distance
58   rule.width = width
59   return rule
60 end
```

`insert_line`

Enclose a rule node (cloze line) with two PDF colorstack whatsits. The first colorstack node dyes the line, the second resets the color.

Node list:

Variable name	Node type	Node subtype	Parameter
<code>n.color_line</code>	whatsit	pdf_colorstack	Line color
<code>n.line</code>	rule		width
<code>n.color_reset</code>	whatsit	pdf_colorstack	Reset color

```
61 function nodex.insert_line(head, current, width)
62   local n = {} -- node
63   n.color_line = nodex.create_color('line')
64   head, n.color_line = node.insert_after(head, current, n.color_line)
65   n.line = nodex.create_line(width)
66   head, n.line = node.insert_after(head, n.color_line, n.line)
67   n.color_reset = nodex.create_color('reset')
68   return node.insert_after(head, n.line, n.color_reset)
69 end
```

`write_line`

This function encloses a rule node with color nodes as it the function `nodex.insert_line` does. In contrast to `nodex.insert_line` the three nodes are appended to TeX's 'current list'. They are not inserted in a node list, which is accessed by a Lua callback.

Node list:

Variable name	Node type	Node subtype	Parameter
-	whatsit	pdf_colorstack	Line color
-	rule		width
-	whatsit	pdf_colorstack	Reset color

```
70 function nodex.write_line()
71   node.write(nodex.create_color('line'))
72   node.write(nodex.create_line(tex.sp(registry.get_value('width'))))
73   node.write(nodex.create_color('reset'))
74 end
```

3.2.1.3 Handling of extendable lines (linefil)

create_linefil

This function creates a line which stretches indefinitely in the horizontal direction.

```
75 function nodex.create_linefil()
76   local glue = node.new('glue')
77   glue.subtype = 100
78   local glue_spec = node.new('glue_spec')
79   glue_spec.stretch = 65536
80   glue_spec.stretch_order = 3
81   glue.spec = glue_spec
82   local rule = nodex.create_line(0)
83   rule.dir = 'TLT'
84   glue.leader = rule
85   return glue
86 end
```

write_linefil

The function `nodex.write_linefil` surrounds a indefinitely stretchable line with color whatsits and puts it to \TeX 's 'current (node) list'.

```
87 function nodex.write_linefil()
88   node.write(nodex.create_color('line'))
89   node.write(nodex.create_linefil())
90   node.write(nodex.create_color('reset'))
91 end
```

3.2.1.4 Kern handling (kern)

create_kern

This function creates a kern node with a given width. The argument width had to be specified in scaled points.

```
92 function nodex.create_kern(width)
93   local kern = node.new(node.id('kern'))
94   kern.kern = width
95   return kern
96 end
```

strut_to_hlist

To make life easier: We add at the beginning of each hlist a strut. Now we can add line, color etc. nodes after the first node of a hlist not before - after is much more easier.

```
97 function nodex.strut_to_hlist(hlist)
98   local n = {} -- node
99   n.head = hlist.head
100  n.kern = nodex.create_kern(0)
101  n.strut = node.insert_before(n.head, n.head, n.kern)
102  hlist.head = n.head.prev
103  return hlist, n.strut, n.head
104 end
```

`write_margin`

Write kern nodes to the current node list. This kern nodes can be used to build a margin.

```
105 function nodex.write_margin()
106   local kern = nodex.create_kern(tex.sp(registry.get_value('margin')))
107   node.write(kern)
108 end
```

3.2.2 Option handling (registry)

The table `registry` bundels functions that deal with option handling.

3.2.2.1 Marker processing (marker)

A marker is a whatsit node of the subtype `user_defined`. A marker has two purposes:

1. Mark the begin and the end of a gap.
2. Store a index number, that points to a Lua table, which holds some additional data like the local options.

`create_marker`

We create a user defined whatsit node that can store a number (type = 100). In order to distinguish this node from other user defined whatsit nodes we set the `user_id` to a large number. We call this whatsit node a marker. The argument `index` is a number, which is associated to values in the `registry.storage` table.

```
109 function registry.create_marker(index)
110   local marker = node.new('whatsit','user_defined')
111   marker.type = 100 -- number
112   marker.user_id = registry.user_id
113   marker.value = index
114   return marker
115 end
```

`write_marker`

Write a marker node to \TeX 's current node list. The argument `mode` accepts the string values `basic`, `fix` and `par`. The argument `position`. The argument `position` is either set to `start` or to `stop`.

```
116 function registry.write_marker(mode, position)
117   local index = registry.set_storage(mode, position)
118   local marker = registry.create_marker(index)
119   node.write(marker)
120 end
```

`check_marker`

This functions tests, whether the given node `item` is a marker. The argument `item` is a node. The argument `mode` accepts the string values `basic`, `fix` and `par`. The argument `position` is either set to `start` or to `stop`.

```

121 function registry.check_marker(item, mode, position)
122   local data = registry.get_marker_data(item)
123   if data and data.mode == mode and data.position == position then
124     return true
125   else
126     return false
127   end
128 end

```

get_marker

registry.get_marker returns the given marker. The argument `item` is a node. The argument `mode` accepts the string values `basic`, `fix` and `par`. The argument `position` is either set to `start` or to `stop`.

```

129 function registry.get_marker(item, mode, position)
130   local out
131   if registry.check_marker(item, mode, position) then
132     out = item
133   else
134     out = false
135   end
136   if out and position == 'start' then
137     registry.get_marker_values(item)
138   end
139   return out
140 end

```

get_marker_data

registry.get_marker_data tests whether the node `item` is a marker. The argument `item` is a node of unspecified type.

```

141 function registry.get_marker_data(item)
142   if item.id == node.id('whatsit')
143     and item.subtype == 44
144     and item.user_id == registry.user_id then
145     return registry.get_storage(item.value)
146   else
147     return false
148   end
149 end

```

get_marker_values

First this function saves the associated values of a marker to the local options table. Second it returns this values. The argument `marker` is a `whatsit` node.

```

150 function registry.get_marker_values(marker)
151   local data = registry.get_marker_data(marker)
152   registry.local_options = data.values
153   return data.values
154 end

```

3.2.2.2 Storage functions (storage)

`get_index`

`registry.index` is a counter. The functions `registry.get_index()` increases the counter by one and then returns it.

```
155 function registry.get_index()
156   if not registry.index then
157     registry.index = 0
158   end
159   registry.index = registry.index + 1
160   return registry.index
161 end
```

`set_storage`

`registry.set_storage()` stores the local options in the Lua table `registry.storage`. It returns a numeric index number. This index number is the key, where the local options in the Lua table are stored. The argument `mode` accepts the string values `basic`, `fix` and `par`.

```
162 function registry.set_storage(mode, position)
163   local index = registry.get_index()
164   local data = {
165     ['mode'] = mode,
166     ['position'] = position
167   }
168   data.values = registry.local_options
169   registry.storage[index] = data
170   return index
171 end
```

`get_storage`

The function `registry.get_storage()` retrieves values which belong to a whatsit marker. The argument `index` is a numeric value.

```
172 function registry.get_storage(index)
173   return registry.storage[index]
174 end
```

3.2.2.3 Option processing (option)

`set_option`

This function stores a value `value` and his associated key `key` either to the global (`registry.global_options`) or to the local (`registry.local_options`) option table. The global boolean variable `registry.local_options` controls in which table the values are stored.

```
175 function registry.set_option(key, value)
176   if value == '' or value == '\\\color@ ' then
177     return false
178   end
179   if registry.is_global == true then
180     registry.global_options[key] = value
```

```

181 else
182     registry.local_options[key] = value
183 end
184 end
set_is_global
    registry.set_is_global() sets the variable registry.is_global to the value
    value. It is intended, that the variable takes boolean values.

185 function registry.set_is_global(value)
186     registry.is_global = value
187 end
unset_local_options
    This function unsets the local options.

188 function registry.unset_local_options()
189     registry.local_options = {}
190 end
unset_global_options
    registry.unset_global_options empties the global options storage.

191 function registry.unset_global_options()
192     registry.global_options = {}
193 end
get_value
    Retrieve a value from a given key. First search for the value in the local options,
    then in the global options. If both option storages are empty, the default value
    will be returned.

194 function registry.get_value(key)
195     if registry.has_value(registry.local_options[key]) then
196         return registry.local_options[key]
197     end
198     if registry.has_value(registry.global_options[key]) then
199         return registry.global_options[key]
200     end
201     return registry.defaults[key]
202 end
get_value_show
    The function registry.get_value_show() returns the boolean value true if the
    option show is true. In contrast to the function registry.get_value() it converts
    the string value 'true' to a boolean value.

203 function registry.get_value_show()
204     if
205         registry.get_value('show') == true
206     or
207         registry.get_value('show') == 'true'
208     then
209         return true
210     else

```

```

211     return false
212 end
213 end
has_value

```

This function tests whether the value `value` is not empty and has a value.

```

214 function registry.has_value(value)
215   if value == nil or value == '' or value == '\\color@ ' then
216     return false
217   else
218     return true
219   end
220 end
get_defaults

```

`registry.get_defaults(option)` returns a the default value of the given option.

```

221 function registry.get_defaults(option)
222   return registry.defaults[option]
223 end

```

3.2.3 Assembly to cloze texts (cloze)

`basic_make`

The function `cloze.basic_make()` makes one gap. The argument `head` is the head node of a node list. The argument `start` is the node, where the gap begins. The argument `stop` is the node, where the gap ends.

```

224 function cloze.basic_make(head, hlist, start, stop)
225   local n = {}
226   local l = {}
227   if not start or not stop then
228     return
229   end
230   n.start = start
231   n.stop = stop
232   l.width = node.dimensions(
233     hlist.glue_set,
234     hlist.glue_sign,
235     hlist.glue_order,
236     n.start,
237     n.stop
238   )
239   head, n.line = nodex.insert_line(head, n.start, l.width)
240   n.color_text = nodex.create_color('text')
241   head, n.color_text = node.insert_after(
242     hlist.head,
243     n.line,
244     n.color_text
245   )
246   if registry.get_value_show() then
247     n.kern = nodex.create_kern(-l.width)

```



```

248     node.insert_after(head, n.color_text, n.kern)
249     n.color_reset = nodex.create_color('reset')
250     node.insert_after(head, n.stop, n.color_reset)
251 else
252     n.line.next = n.stop.next
253     n.stop.prev = n.line.prev
254 end
255
256 end

```

basic

The corresponding L^AT_EX command to this lua function is `\cloze` (→ 2.1.1). The argument `head` is the head node of a node list.

```

257 function cloze.basic(head)
258     local n = {} -- node
259     local b = {} -- boolean
260     local l = {} -- length
261     local t = {} -- temp
262     for hlist in node.traverse_id(node.id('hlist'), head) do
263         hlist = nodex.strut_to_hlist(hlist)
264         if b.line_end then
265             b.init_cloze = true
266         end
267         n.current = hlist.head
268         while n.current do
269             if
270                 registry.check_marker(n.current, 'basic', 'start')
271             or
272                 b.init_cloze
273             then
274                 b.init_cloze = false
275                 n.start = n.current
276                 while n.current do
277                     b.line_end = true
278                     n.stop = n.current
279                     if registry.check_marker(n.stop, 'basic', 'stop') then
280                         b.line_end = false
281                         break
282                     end
283                     n.current = n.current.next
284                 end
285                 cloze.basic_make(head, hlist, n.start, n.stop)
286                 n.current = n.stop
287             else
288                 n.current = n.current.next
289             end
290         end
291     end
292     return head
293 end

```

fix_make

The function `cloze.fix_make` generates a gap of fixed width.

Node lists

Show text:

Variable name	Node type	Node subtype	Parameter
n.start	whatsit	user_defined	index
n.line	rule		l.width
n.kern_start	kern		Depends on align
n.color_text	whatsit	pdf_colorstack	Text color
	glyphs		Text to show
n.color_reset	whatsit	pdf_colorstack	Reset color
n.kern_stop	kern		Depends on align
n.stop	whatsit	user_defined	index

Hide text:

Variable name	Node type	Node subtype	Parameter
n.start	whatsit	user_defined	index
n.line	rule		l.width
n.stop	whatsit	user_defined	index

The argument `head` is the head node of a node list. The argument `start` is the node, where the gap begins. The argument `stop` is the node, where the gap ends.

```
294 function cloze.fix_make(head, start, stop)
295   local l = {} -- length
296   l.width = tex.sp(registry.get_value('width'))
297   local n = {} -- node
298   n.start = start
299   n.stop = stop
300   l.text_width = node.dimensions(n.start, n.stop)
301   local align = registry.get_value('align')
302   if align == 'right' then
303     l.kern_start = -l.text_width
304     l.kern_stop = 0
305   elseif align == 'center' then
306     l.half = (l.width - l.text_width) / 2
307     l.kern_start = -l.half - l.text_width
308     l.kern_stop = l.half
309   else
310     l.kern_start = -l.width
311     l.kern_stop = l.width - l.text_width
312   end
313   head, n.line = nodex.insert_line(head, n.start, l.width)
314   if registry.get_value_show() then
315     n.kern_start = nodex.create_kern(l.kern_start)
316     head, n.kern_start = node.insert_after(head, n.line, n.kern_start)
317     n.color_text = nodex.create_color('text')
318     node.insert_after(head, n.kern_start, n.color_text)
319     n.color_reset = nodex.create_color('reset')
320     node.insert_before(head, n.stop, n.color_reset)
321     n.kern_stop = nodex.create_kern(l.kern_stop)
322     node.insert_before(head, n.stop, n.kern_stop)
```

```

323 else
324   n.line.next = n.stop.next
325 end
326 end
fix

```

The corresponding L^AT_EXcommand to this Lua function is `\clozefix` (→ 2.1.3).
The argument `head` is the head node of a node list.

```

327 function cloze.fix(head)
328   local n = {} -- node
329   n.start, n.stop = false
330   for current in node.traverse_id(node.id('whatsit'), head) do
331     if not n.start then
332       n.start = registry.get_marker(current, 'fix', 'start')
333     end
334     if not n.stop then
335       n.stop = registry.get_marker(current, 'fix', 'stop')
336     end
337     if n.start and n.stop then
338       cloze.fix_make(head, n.start, n.stop)
339       n.start, n.stop = false
340     end
341   end
342   return head
343 end

```

par

The corresponding L^AT_EXenvironment to this lua function is `clozepar` (→ 2.1.5).

Node lists

Show text:

Variable name	Node type	Node subtype	Parameter
n.strut	kern		width = 0
n.line	rule		l.width (Width from hlist)
n.kern	kern		-l.width
n.color_text	whatsit	pdf_colorstack	Text color
	glyphs		Text to show
n.tail	glyph		Last glyph in hlist
n.color_reset	whatsit	pdf_colorstack	Reset color

Hide text:

Variable name	Node type	Node subtype	Parameter
n.strut	kern		width = 0
n.line	rule		l.width (Width from hlist)

The argument `head` is the head node of a node list.

```

344 function cloze.par(head)
345   local l = {} -- length
346   local n = {} -- node
347   for hlist in node.traverse_id(node.id('hlist'), head) do
348     for whatsit in node.traverse_id(node.id('whatsit'), hlist.head) do
349       registry.get_marker(whatsit, 'par', 'start')
350     end

```

```

351     l.width = hlist.width
352     hlist, n.strut, n.head = nodex.strut_to_hlist(hlist)
353     head, n.line = nodex.insert_line(head, n.strut, l.width)
354     if registry.get_value_show() then
355         n.kern = nodex.create_kern(-l.width)
356         head, n.kern = node.insert_after(head, n.line, n.kern)
357         n.color_text = nodex.create_color('text')
358         node.insert_after(head, n.kern, n.color_text)
359         n.tail = node.tail(n.head)
360         n.color_reset = nodex.create_color('reset')
361         node.insert_after(n.head, n.tail, n.color_reset)
362     else
363         n.line.next = nil
364     end
365 end
366 return head
367 end

```

3.2.4 Basic module functions (base)

register The base table contains functions which are published to the `cloze.sty` file. This function registers the functions `cloze.par`, `cloze.basic` and `cloze.fix` the Lua callbacks. `cloze.par` and `cloze.basic` are registered to the callback `post_linebreak_filter` and `cloze.fix` to the callback `pre_linebreak_filter`. The argument `mode` accepts the string values `basic`, `fix` and `par`.

```

368 function base.register(mode)
369   if mode == 'par' then
370     luatexbase.add_to_callback(
371       'post_linebreak_filter',
372       cloze.par,
373       mode
374     )
375     return true
376   end
377   if not base.is_registered[mode] then
378     if mode == 'basic' then
379       luatexbase.add_to_callback(
380         'post_linebreak_filter',
381         cloze.basic,
382         mode
383       )
384     elseif mode == 'fix' then
385       luatexbase.add_to_callback(
386         'pre_linebreak_filter',
387         cloze.fix,
388         mode
389       )
390     else

```

```

391     return false
392   end
393   base.is_registered[mode] = true
394 end
395 end
unregister

```

`base.unregister(mode)` deletes the registered functions from the Lua callbacks. The argument `mode` accepts the string values `basic`, `fix` and `par`.

```

396 function base.unregister(mode)
397   if mode == 'basic' then
398     luatexbase.remove_from_callback('post_linebreak_filter', mode)
399   elseif mode == 'fix' then
400     luatexbase.remove_from_callback('pre_linebreak_filter', mode)
401   else
402     luatexbase.remove_from_callback('post_linebreak_filter', mode)
403   end
404 end

```

Publish some functions to the `cloze.sty` file.

```

405 base.linefil = nodex.write_linefil
406 base.line = nodex.write_line
407 base.margin = nodex.write_margin
408 base.set_option = registry.set_option
409 base.set_is_global = registry.set_is_global
410 base.unset_local_options = registry.unset_local_options
411 base.reset = registry.unset_global_options
412 base.get_defaults = registry.get_defaults
413 base.marker = registry.write_marker

414 return base

```

Change History

v0.1		v1.0	
General: Converted to DTX file . . .	8	General: Inital release	8

Index

Numbers written in *italic* refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in *roman* refer to the code lines where the entry is used.

Symbols		
<code>\\</code>	176, 215	
C		
<code>\cloze</code>	<u>114</u> , 145	
<code>\cloze@color</code>	<u>42</u> , 78, 88	
<code>\cloze@margin</code> <u>58</u> , 119, 128	
<code>\cloze@set@local@options</code>	<u>43</u> , 115, 124, 135, 148, 152	
<code>\cloze@set@option</code>	<u>39</u> , 69, 71, 73, 74, 78, 81, 83, 84, 88, 91, 93	
<code>\cloze@set@to@global</code>	<u>30</u> , 63, 96	
<code>\cloze@set@to@local</code>	<u>33</u> , 44	
<code>\cloze@start@marker</code>	<u>47</u> , 116, 125, 136	
<code>\cloze@stop@marker</code>	<u>53</u> , 121, 130, 140	
<code>\clozefil</code>	<u>144</u>	
<code>\clozefix</code>	<u>123</u>	
<code>\clozefont</code>	<u>108</u> , 110, 118, 127, 137	
<code>\clozehide</code>	<u>105</u>	
<code>\clozeline</code>	<u>147</u>	
<code>\clozelinefil</code>	145, <u>151</u>	
<code>clozepar</code> (environ- ment)	<u>132</u>	
<code>\clozereset</code>	<u>99</u>	
<code>\clozeset</code>	<u>95</u> , 103, 106	
<code>\clozesetfont</code>	<u>109</u>	
<code>\clozeshow</code>	<u>102</u>	
<code>\color@</code>	42	
<code>\csname</code>	42	
D		
<code>\DeclareStringOption</code>	68, 70, 76, 80, 86, 90, 92	
<code>\DeclareVoidOption</code>	72, 82	
<code>\define@key</code>	69, 71, 77, 81, 87, 91, 93	
E		
<code>\endcsname</code>	42	
environments:		
<code>clozepar</code>	<u>132</u>	
I		
<code>\itshape</code>	108	
K		
<code>\kvsetkeys</code>	45, 97	
P		
<code>\par</code>	134, 141	
<code>\ProcessKeyvalOptions</code>	94	
R		
<code>\relax</code>	118, 127, 137	
<code>\renewcommand</code>	110	
<code>\RequirePackage</code>	26	
S		
<code>\SetupKeyvalOptions</code>	64	
<code>\string</code>	42	
<code>\strut</code>	48, 54, 153, 155	